

# Carl Boyd Designs



Sea Spray

## Materials

Yeoman Panama 4ply Cotton and Acrylic  
Colour 214 Spray  
1 Cone for first 2 sizes, 2 Cones for remainder

## Sizes

To fit Bust 34 (36:38:40:42:44) inches  
87 (92:97:102:107:112) cm  
Actual all round measurement 38 (40:42:44:46:48) inches  
97 (102:107:112:117:122) cm

## Main Tension

30sts and 40 rows to 10cm measured over stocking stitch after sample has been washed and lightly pressed.

## Machines

These instructions are written for standard gauge machines with ribber or Electronic machines. Garment illustrated was knit on a Brother 965 electronic.

## Notes

All decreases and increases are made fully fashioned using a 3 pronged transfer tool. **6 sts extra** have been allowed on front to counteract the pull in effect of the 3 cables.

## Selvedge edge

To get a really neat selvedge edge this is the method I use to cast on.  
TD0 on both beds knit 1 row and hang comb and weights. Up tension by 2 clicks on both beds, knit circular rows. TD1 on both beds, knit closing row. If too difficult on your machine keep moving up 1 click at a time.

## Back

Push 144 (152:160:168:176:184) Ns to WP on both beds for full needle rib. With MY cast on and knit selvedge. RC000 TD3 knit 20 rows and transfer sts to main bed. RC000 TD7 knit to RC124 and put a marker at each end. Decrease 1 st each end the next and every following alternate row to RC164 (20 dec. made each side). Continue straight to RC220 and divide for back neck shaping. Put a marker between centre Ns. Cast off the centre 44(44:46:48:52:52) sts and put Ns on left to hold position. Working on the right side knit 1 row. Cast off 4st on neck edge on the next and following alternate row 3 times (RC226). Start shoulder slope. Cast off 5(6:7:8:9:10)sts beg next row, on neck edge cast of 2 sts beginning next row (14 dec made on neck edge). Cast off 5(6:8:9:9:11)sts beg next row, knit 1 row. Cast off remaining 6 (8:8:9:10:11:) sts and complete left side to match right reversing shapings.

## Front

Push 150:158:166:174:182:190) Ns to WP on both beds for full needle rib. With MY cast on and knit selvedge. RC000 TD2 knit 20 rows and transfer sts to main bed, leave ribber in position. **Cable Panel.** On right side of machine transfer the stitches on Ns 4&5, 10&11, 18&19 to the ribber. Repeat on left of machine making 3 cables of 6 sts with 4 sts in between each cable. RC000 TD7 10 rows and cable sts. Continuing to cable every 10 rows knit to RC124 and put a marker at each end. Decrease 1 st each end the next and every following alternate row to RC164 (20 dec. made each side). Continue straight to RC180 and divide for front neck shaping. Transfer all sts on ribber to main bed, drop ribber and change carriage. Put a marker between centre Ns. Cast off the centre 30(30:32:34:36:38)sts and put Ns on left to hold position. Working on the right side knit 1 row, on neck edge cast off 4 sts beg next row. Knit 1 row, cast off 3 sts beg next row, knit 1 row. Cast off 2 sts beg next and following alt row 4 times. Knit 1 row . Dec 1st beg

next and every following alternate row 6 times, knit 1 row. Dec 1 st every following 4<sup>th</sup> row 3 times(24 decs made on neck edge) Work straight to RC226. Start shoulder slope. Start shoulder slope. Cast off 5(6:7:8:9:10)sts beg next row, knit 1 row. Cast off 5(6:8:9:9:11)sts beg next row, knit 1 row. Cast off remaining 6 (8:8:9:10:11:) sts and complete left side to match right reversing shapings.

### **Sleeves**

Push 72(74:76:78:80:82) Ns to WP on both beds for full nd rib. With MY cast on and knit selvedge. RC000 TD2 knit 20 rows and transfer sts to main bed. Increases on the sleeve are worked fully fashioned. For those not sure move 2 sts outwards and take the heel of the 3rd st and place on empty Nd. RC000 TD7 Knit 2 rows, increasing 1st at each end of the next and every following 5th row knit to RC28 when you will have 84(86:88:90:92:94)Ns in work. Knit to RC31, increasing 1 st each end of the next and every following 6th row knit to RC116 when you will have 114(116:118:120:122:124) Ns in WP. Knit to RC120 and put a marker at each end of row. Decreasing on the next and every following alternate row knit to RC160 (20 dec. made each side). Now decrease 1<sup>st</sup> each end of every row to RC182 (22 dec. made each side). Now decrease 1<sup>st</sup> each end next and every following alternate row 3 times RC188. Place a marker between 2 centre Ns and cast off remaining 24(26:28:30:32:34) sts.

### **Collar Front**

Push 56Ns to WP each side of centre (112 Ns) on main bed, with wrong side facing you pick up centre of neck onto the 2 centre Ns. Place the extreme outside edge of neckline on Ns 56 at each end, pick up remaining neck edge onto remaining Ns and hang a claw weight at each end. TD5 knit 1 row, TD6 knit one row. **If you are not going to put pearls around the neck the following transfers can be ignored.** Set RC000, starting on the left transfer the st on Nd50 to adjacent Nd on the right, then transfer the st on Ns 40, 30, 20and 10 to adjacent Nd. Transfer the st on the Nd. right of centre to Nd.2, then transfer st 11, 21, 31 etc. on the right of machine bed, to adjacent Nd. You should have 9 Nds in work between each transfer.TD6 knit 26 rows and cast off.

### **Collar Back**

Push 36 Ns to WP each side of centre (72 Ns) and pick up back neck as for front. TD5 knit 1 row, TD6 knit one row. RC000 transfer sts as for front starting on Nd 30 left to Nd 31 Right. TD6 knit 26 rows and cast off.

### **To Make UP**

Block all pieces to shape and press according to yarn label. Join shoulder seams and seam of roll collar. Roll the collar quite tightly into position. Working on the back neck and with right side facing starting with the last hole on the right shoulder thread pearls through going under the roll on the right side of sweater pulling through to last pearl, anchor pearl in place under roll. Bring pearls over the roll and back under going through next hole. Continue in this manner until you are back were you started and leave remaining pearls hanging loose for the time being. Make sure roll is over the seam created when you picked up the neck, working from inside slipstitch the seam to the roll to hold it in place taking care not to catch the pearls. On right side you can now adjust the pearls as necessary till you get them evenly spaced (see close up photograph). Once satisfied snip off remaining pearls and anchor the last one next to the one already anchored. Thread pearls (optional) through cable as shown in previous article and anchor into position on wrong side of sweater. Set sleeves into armhole and press seam. Mattress stitch cuff and welt and join side and sleeve seams and press.

A 48, 50.5, 53, 56, 58.5, 61cm  
B 6 cm  
C 30.5  
D 25.5, 25.5, 26, 26, 26.5, 26.5 cm  
E 35, 37.5, 40, 43, 45, 48  
F 20, 20.5, 21, 21.5, 22, 22.5 cm  
G 24 cm  
H 30 cm  
I 17 cm  
J 39, 39.5, 40, 40.5, 41, 41.5 cm  
K 9, 9.5, 10, 10.5, 11, 11.5 cm  
Back neck depth 1.5 cm  
Front neck depth 12.5 cm

